

# The `settobox` package

Heiko Oberdiek\*

2016/05/16 v1.5

## Abstract

Commands are defined for getting box sizes similar to L<sup>A</sup>T<sub>E</sub>X's `\settowidth` commands.

## Contents

|  |          |
|--|----------|
| <b>1 Usage</b>   | <b>2</b> |
| 1.1 Get box dimensions . . . . .                       | 2        |
| 1.2 Set box dimensions . . . . .                       | 2        |
| 1.3 Move box . . . . .                                 | 2        |
| 1.4 Example . . . . .                                  | 2        |
| 1.4.1 Short example . . . . .                          | 2        |
| 1.4.2 Test file that shows box manipulations . . . . . | 2        |
| <b>2 Implementation</b>                                | <b>5</b> |
| <b>3 Installation</b>                                  | <b>6</b> |
| 3.1 Download . . . . .                                 | 6        |
| 3.2 Bundle installation . . . . .                      | 7        |
| 3.3 Package installation . . . . .                     | 7        |
| 3.4 Refresh file name databases . . . . .              | 7        |
| 3.5 Some details for the interested . . . . .          | 7        |
| <b>4 History</b>                                       | <b>8</b> |
| [2000/02/11 v1.0] . . . . .                            | 8        |
| [2000/09/07 v1.1] . . . . .                            | 8        |
| [2006/02/20 v1.2] . . . . .                            | 8        |
| [2007/04/11 v1.3] . . . . .                            | 8        |
| [2008/08/11 v1.4] . . . . .                            | 8        |
| [2016/05/16 v1.5] . . . . .                            | 8        |
| <b>5 Index</b>   | <b>8</b> |

---

\*Please report any issues at <https://github.com/ho-tex/oberdiek/issues>

# 1 Usage

## 1.1 Get box dimensions

```
\setboxwidth{\langle LATEX length \rangle}{\langle LATEX box \rangle}  
\setboxheight{\langle LATEX length \rangle}{\langle LATEX box \rangle}  
\setboxdepth{\langle LATEX length \rangle}{\langle LATEX box \rangle}  
\setboxtotalheight{\langle LATEX length \rangle}{\langle LATEX box \rangle}
```

A  $\langle L^A T_E X box \rangle$  is allocated by `\newsavebox`. It can be filled by `\sbox` or the environment `lrbox`. The commands above extract then the desired lengths.

## 1.2 Set box dimensions

```
\setboxwidth{\langle LATEX box \rangle}{\langle LATEX length expression \rangle}  
\setboxheight{\langle LATEX box \rangle}{\langle LATEX length expression \rangle}  
\setboxdepth{\langle LATEX box \rangle}{\langle LATEX length expression \rangle}
```

These commands allow the manipulation of the box. Package `calc` is supported in the  $\langle L^A T_E X length expression \rangle$ . Also the following length are available in this expression:

|                           |                        |
|---------------------------|------------------------|
| <code>\width</code>       | width of the box       |
| <code>\height</code>      | height of the box      |
| <code>\depth</code>       | depth of the box       |
| <code>\totalheight</code> | totalheight of the box |

Note, the base point (point at the left margin of the baseline) always remain constant.

## 1.3 Move box

```
\setboxmoveleft{\langle LATEX box \rangle}{\langle LATEX length expression \rangle}  
\setboxmoveright{\langle LATEX box \rangle}{\langle LATEX length expression \rangle}  
\setboxlower{\langle LATEX box \rangle}{\langle LATEX length expression \rangle}  
\setboxright{\langle LATEX box \rangle}{\langle LATEX length expression \rangle}
```

Note, the box is shifted relative to the base point. The base point is always inside the box, however the width and height of the box change along with the movement.

## 1.4 Example

### 1.4.1 Short example

```
\newsavebox{\mybox}  
\newlength{\mylength}  
\sbox{\mybox}{Hello World}  
\setboxwidth{\mylength}{\mybox}
```

### 1.4.2 Test file that shows box manipulations

```
1 (*example)  
2 %<<END  
3 \documentclass{article}
```

```

4
5 \usepackage{settoebox}
6 \usepackage{calc}
7
8 \newsavebox{\mybox}
9
10 \setlength{\fboxsep}{0pt}
11 \setlength{\parindent}{20pt}
12 \setlength{\parskip}{10pt}
13 \pagestyle{empty}
14
15 % \test{#1}
16 % The macro is called with commands in #1 that manipulates
17 % the box \mybox. These commands along with the result of
18 % the manipulation is shown. Thus the essence of the
19 % macro is:
20 %
21 % a) \sbox{\mybox}{The cracy fox.}
22 % b) #1 % manipulates \mybox
23 % c) Print #1 commands.
24 % d) Print box with frame
25 %
26 % The implemenation looks more weird:
27 \makeatletter
28 \newcommand*\test}[1]{%
29   \par
30   \begingroup
31     \raggedright
32     \edef\x{\detokenize{#1}}%
33     \let\do\makeoother
34     \dospecials
35     \catcode'\~\active
36     \catcode'\ =10\relax
37     \def~{\}%
38     \noindent
39     \texttt{\scantokens\expandafter{\x}}%
40     \par
41   \endgroup
42   \begingroup
43     \let~\relax
44     \sbox{\mybox}{The cracy fox.}%
45     #1%
46     A---\fbox{\usebox\mybox}---B%
47   \endgroup
48   \par
49 }
50 \makeatother
51
52 \begin{document}
53
54 \test{\setboxwidth{\mybox}{1.25\width}}
55 \test{\setboxheight{\mybox}{0pt}}
56 \test{\setboxheight{\mybox}{2\height}}
57 \test{\setboxdepth{\mybox}{\height}}
58 \test{\setboxmoveleft{\mybox}{5pt}}
59 \test{%
60   \setboxmoveleft{\mybox}{5pt}~%
61   \setboxwidth{\mybox}{\width + 5pt}%

```

```

62 }
63 \test{\setboxmoveright{\mybox}{0.5\width}}
64 \test{\setboxlower{\mybox}{\height}}
65 \test{\setboxraise{\mybox}{\depth}}
66 \test{%
67   \setboxmoveright{\mybox}{5pt}~%
68   \setboxwidth{\mybox}{\width + 5pt}~%
69   \setboxheight{\mybox}{\height + 5pt}~%
70   \setboxdepth{\mybox}{\depth + 5pt}%
71 }
72
73 \end{document}
74 %END
75 \end{example}

```

The result:

---

```
\setboxwidth {\mybox }{1.25\width }
```

A—The cracy fox.—B

```
\setboxheight {\mybox }{0pt}
```

A—The cracy fox.—B

```
\setboxheight {\mybox }{2\height }
```

A—The cracy fox.—B

```
\setboxdepth {\mybox }{\height }
```

A—The cracy fox.—B

```
\setboxmoveleft {\mybox }{5pt}
```

A—The cracy fox.—B

```
\setboxmoveleft {\mybox }{5pt}
```

```
\setboxwidth {\mybox }{\width + 5pt}
```

A—The cracy fox.—B

```
\setboxmoveright {\mybox }{0.5\width }
```

A—The cracy fox.—B

```
\setboxlower {\mybox }{\height }
```

A—The cracy fox.—B

```
\setboxraise {\mybox }{\depth }
```

A—The cracy fox.—B

```
\setboxmoveright {\mybox }{5pt}
```

```
\setboxwidth {\mybox }{\width + 5pt}
```

```
\setboxheight {\mybox }{\height + 5pt}
```

```
\setboxdepth {\mybox }{\depth + 5pt}
```

A—The cracy fox.—B

---

## 2 Implementation

```
76 (*package)
```

Package identification.

```
77 \NeedsTeXFormat{LaTeX2e}
```

```
78 \ProvidesPackage{settoebox}%
```

```
79 [2016/05/16 v1.5 Assign box dimensions to length registers (HO)]
```

```
80 \newcommand*\settoeboxwidth}[2]{\setlength{#1}{\wd#2}}
```

```
81 \newcommand*\settoeboxheight}[2]{\setlength{#1}{\ht#2}}
```

```
82 \newcommand*\settoeboxdepth}[2]{\setlength{#1}{\dp#2}}
```

```
83 \newcommand*\settoeboxtotalheight}[2]{%
```

```
84 \setlength{#1}{\ht#2}%,
```

```
85 \addtolength{#1}{\dp#2}%,
```

```
86 }
```

`\setboxwidth`

```
87 \newcommand*\setboxwidth}[2]{%
```

```
88 \settoebox@length\wd{#1}{#2}%,
```

```
89 }
```

`\setboxheight`

```
90 \newcommand*\setboxheight}[2]{%
```

```
91 \settoebox@length\ht{#1}{#2}%,
```

```
92 }
```

`\setboxdepth`

```
93 \newcommand*\setboxdepth}[2]{%
```

```
94 \settoebox@length\dp{#1}{#2}%,
```

```
95 }
```

`\setboxmoveleft`

```
96 \newcommand*\setboxmoveleft}[2]{%
```

```
97 \settoebox@horiz{-}{#1}{#2}%,
```

```
98 }
```

`\setboxmoveright`

```
99 \newcommand*\setboxmoveright}[2]{%
```

```
100 \settoebox@horiz{#1}{#2}%,
```

```
101 }
```

`\setboxlower`

```
102 \newcommand*\setboxlower}[2]{%
```

```
103 \settoebox@vert\lower{#1}{#2}%,
```

```
104 }
```

`\setboxraise`

```
105 \newcommand*\setboxraise}[2]{%
```

```
106 \settoebox@vert\raise{#1}{#2}%,
```

```
107 }
```

```

\settobox@length The work for the \setbox... commands is done by \settobox@length. Inside
the length expression \width, \height, \depth, \totalheight are set to the
dimensions of the box.
#1: the property of the box that is to be changed (\wd, \ht, \dp)
#2: the box
#3: length expression
108 \def\settobox@length#1#2#3{%
109 \settobox@calc{#2}{#3}{#1#2=##1sp\relax}%
110 }

\settobox@horiz
111 \def\settobox@horiz#1#2#3{%
112 \settobox@calc{#2}{#3}{\setbox#2=\hbox{\kern#1##1sp\copy#2}}%
113 }

\settobox@vert
114 \def\settobox@vert#1#2#3{%
115 \settobox@calc{#2}{#3}{\setbox#2=\hbox{#1##1sp\copy#2}}%
116 }

\settobox@calc
117 \def\settobox@calc#1#2#3{%
118 \begingroup
119 \def\width{\wd#1}%
120 \def\height{\ht#1}%
121 \def\depth{\dp#1}%
122 \dimen@\ht#1\relax
123 \advance\dimen@\dp#1\relax
124 \def\totalheight{\dimen@}%
125 \setlength{\dimen@}{#2}%
126 \count@\dimen@
127 \def\x##1{\endgroup
128 #3%
129 }%
130 \expandafter\x\expandafter{\the\count@}%
131 }

132 </package>

```

## 3 Installation

### 3.1 Download

**Package.** This package is available on CTAN<sup>1</sup>:

[CTAN:macros/latex/contrib/oberdiek/settobox.dtx](https://ctan.org/ctan/packages/macros/latex/contrib/oberdiek/settobox.dtx) The source file.

[CTAN:macros/latex/contrib/oberdiek/settobox.pdf](https://ctan.org/ctan/packages/macros/latex/contrib/oberdiek/settobox.pdf) Documentation.

**Bundle.** All the packages of the bundle ‘oberdiek’ are also available in a TDS compliant ZIP archive. There the packages are already unpacked and the documentation files are generated. The files and directories obey the TDS standard.

[CTAN:install/macros/latex/contrib/oberdiek.tds.zip](https://ctan.org/ctan/packages/install/macros/latex/contrib/oberdiek.tds.zip)

TDS refers to the standard “A Directory Structure for T<sub>E</sub>X Files” ([CTAN:pkg/tds](https://ctan.org/ctan/packages/pkg/tds)). Directories with `texmf` in their name are usually organized this way.

---

<sup>1</sup>[CTAN:pkg/settobox](https://ctan.org/ctan/packages/pkg/settobox)

## 3.2 Bundle installation

**Unpacking.** Unpack the `oberdiek.tds.zip` in the TDS tree (also known as `texmf` tree) of your choice. Example (linux):

```
unzip oberdiek.tds.zip -d ~/texmf
```

## 3.3 Package installation

**Unpacking.** The `.dtx` file is a self-extracting `docstrip` archive. The files are extracted by running the `.dtx` through plain `TEX`:

```
tex settobox.dtx
```

**TDS.** Now the different files must be moved into the different directories in your installation TDS tree (also known as `texmf` tree):

```
settobox.sty      → tex/latex/oberdiek/settobox.sty
settobox.pdf      → doc/latex/oberdiek/settobox.pdf
settobox-example.tex → doc/latex/oberdiek/settobox-example.tex
settobox.dtx      → source/latex/oberdiek/settobox.dtx
```

If you have a `docstrip.cfg` that configures and enables `docstrip`'s TDS installing feature, then some files can already be in the right place, see the documentation of `docstrip`.

## 3.4 Refresh file name databases

If your `TEX` distribution (`TEX Live`, `MiKTEX`, ...) relies on file name databases, you must refresh these. For example, `TEX Live` users run `texhash` or `mktextlsr`.

## 3.5 Some details for the interested

**Unpacking with L<sup>A</sup>T<sub>E</sub>X.** The `.dtx` chooses its action depending on the format:

**plain T<sub>E</sub>X:** Run `docstrip` and extract the files.

**L<sup>A</sup>T<sub>E</sub>X:** Generate the documentation.

If you insist on using L<sup>A</sup>T<sub>E</sub>X for `docstrip` (really, `docstrip` does not need L<sup>A</sup>T<sub>E</sub>X), then inform the autodetect routine about your intention:

```
latex \let\install=y\input{settobox.dtx}
```

Do not forget to quote the argument according to the demands of your shell.

**Generating the documentation.** You can use both the `.dtx` or the `.drv` to generate the documentation. The process can be configured by the configuration file `ltxdoc.cfg`. For instance, put this line into this file, if you want to have A4 as paper format:

```
\PassOptionsToClass{a4paper}{article}
```

An example follows how to generate the documentation with pdfL<sup>A</sup>T<sub>E</sub>X:

```
pdflatex settobox.dtx
makeindex -s gind.ist settobox.idx
pdflatex settobox.dtx
makeindex -s gind.ist settobox.idx
pdflatex settobox.dtx
```

## 4 History

[2000/02/11 v1.0]

- First public release, written as answer in the newsgroup [de.comp.text.tex](#): “Die Hoehe von Minipages und Bild”<sup>2</sup>

[2000/09/07 v1.1]

- Documentation added.
- CTAN release.

[2006/02/20 v1.2]

- `\setboxwidth`, `\setboxheight`, `\setboxdepth` added.
- Box move commands added.
- DTX framework.
- LPPL 1.3

[2007/04/11 v1.3]

- Line ends sanitized.

[2008/08/11 v1.4]

- Code is not changed.
- URLs updated.

[2016/05/16 v1.5]

- Documentation updates.

## 5 Index

Numbers written in *italic* refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; plain numbers refer to the code lines where the entry is used.

| Symbols                         |            | B                              |                                |
|---------------------------------|------------|--------------------------------|--------------------------------|
| <code>\@makeother</code> .....  | <i>33</i>  | <code>\begin</code> .....      | <i>52</i>                      |
| <code>\@</code> .....           | <i>37</i>  | <b>C</b>                       |                                |
| <code>\~</code> .....           | <i>35</i>  | <code>\catcode</code> .....    | <i>35, 36</i>                  |
|                                 |            | <code>\copy</code> .....       | <i>112, 115</i>                |
| <code>\_</code> .....           | <i>36</i>  | <code>\count@</code> .....     | <i>126, 130</i>                |
| <b>A</b>                        |            | <b>D</b>                       |                                |
| <code>\active</code> .....      | <i>35</i>  | <code>\depth</code> .....      | <i>65, 70, 121</i>             |
| <code>\addtolength</code> ..... | <i>85</i>  | <code>\detokenize</code> ..... | <i>32</i>                      |
| <code>\advance</code> .....     | <i>123</i> | <code>\dimen@</code> .....     | <i>122, 123, 124, 125, 126</i> |
|                                 |            | <code>\do</code> .....         | <i>33</i>                      |

<sup>2</sup>Url: <https://groups.google.com/group/de.comp.text.tex/msg/c3f6446f54f66c02>



|   |   |   |   |
|---|---|---|---|
| <code>\documentclass</code> .....                       | 3   | <b>R</b>  |   |
| <code>\dospecials</code> .....                          | 34  | <code>\raggedright</code> .....                         | 31  |
| <code>\dp</code> .....                                  | 82, 85, 94, 121, 123  | <code>\raise</code> .....                               | 106   |
| <b>E</b>  |   | <b>S</b>  |   |
| <code>\end</code> .....                                 | 73  | <code>\sbox</code> .....                                | 21, 44  |
| <b>F</b>  |   | <code>\scantokens</code> .....                          | 39  |
| <code>\fbox</code> .....                                | 46  | <code>\setbox</code> .....                              | 112, 115  |
| <code>\fboxsep</code> .....                             | 10  | <code>\setboxdepth</code> .....                         | 2, 57, 70, 93                                     |
| <b>H</b>  |   | <code>\setboxheight</code> .....                        | 2, 55, 56, 69, 90, 93                             |
| <code>\hbox</code> .....                                | 112, 115  | <code>\setboxlower</code> .....                         | 2, 64, 102  |
| <code>\height</code> .....                              | 56, 57, 64, 69, 120   | <code>\setboxmoveleft</code> .....                      | 2, 58, 60, 96                                     |
| <code>\ht</code> .....                                  | 81, 84, 91, 120, 122  | <code>\setboxmoveright</code> .....                     | 2, 63, 67, 99                                     |
| <b>K</b>  |   | <code>\setboxraise</code> .....                         | 65, 105   |
| <code>\kern</code> .....                                | 112   | <code>\setboxright</code> .....                         | 2   |
| <b>L</b>  |   | <code>\setboxwidth</code> .....                         | 2, 54, 61, 68, 87                                 |
| <code>\lower</code> .....                               | 103   | <code>\setlength</code> 10, 11, 12, 80, 81, 82, 84, 125 |   |
| <b>M</b>  |   | <code>\settobox@calc</code> .....                       | 109, 112, 115, 117                                |
| <code>\makeatletter</code> .....                        | 27  | <code>\settobox@horiz</code> .....                      | 97, 100, 111                                      |
| <code>\makeatother</code> .....                         | 50  | <code>\settobox@length</code> .....                     | 88, 91, 94, 108                                   |
| <code>\mybox</code> .....                               | 8,<br>17, 21, 22, 44, 46, 54, 55, 56, 57,<br>58, 60, 61, 63, 64, 65, 67, 68, 69, 70 | <code>\settobox@vert</code> .....                       | 103, 106, 114                                     |
| <b>N</b>  |   | <code>\settoboxdepth</code> .....                       | 2, 82   |
| <code>\NeedsTeXFormat</code> .....                      | 77  | <code>\settoboxheight</code> .....                      | 2, 81   |
| <code>\newcommand</code> .....                          | 28, 80, 81,<br>82, 83, 87, 90, 93, 96, 99, 102, 105                                 | <code>\settoboxtotalheight</code> .....                 | 2, 83   |
| <code>\newsavebox</code> .....                          | 8   | <code>\settoboxwidth</code> .....                       | 2, 80   |
| <code>\noindent</code> .....                            | 38  | <b>T</b>  |   |
| <b>P</b>  |   | <code>\test</code> .....                                | 15, 28,<br>54, 55, 56, 57, 58, 59, 63, 64, 65, 66 |
| <code>\pagestyle</code> .....                           | 13  | <code>\texttt</code> .....                              | 39  |
| <code>\par</code> .....                                 | 29, 40, 48  | <code>\the</code> .....                                 | 130   |
| <code>\parindent</code> .....                           | 11  | <code>\totalheight</code> .....                         | 124   |
| <code>\parskip</code> .....                             | 12  | <b>U</b>  |   |
| <code>\ProvidesPackage</code> .....                     | 78  | <code>\usebox</code> .....                              | 46  |
| <b>R</b>  |   | <code>\usepackage</code> .....                          | 5, 6  |
| <b>S</b>  |   | <b>W</b>  |   |
| <code>\sbox</code> .....                                | 21, 44  | <code>\wd</code> .....                                  | 80, 88, 119                                       |
| <code>\scantokens</code> .....                          | 39  | <code>\width</code> .....                               | 54, 61, 63, 68, 119                               |
| <code>\setbox</code> .....                              | 112, 115  | <b>X</b>  |   |
| <code>\setboxdepth</code> .....                         | 2, 57, 70, 93   | <code>\x</code> .....                                   | 32, 39, 127, 130                                  |
| <code>\setboxheight</code> .....                        | 2, 55, 56, 69, 90, 93   |   |   |
| <code>\setboxlower</code> .....                         | 2, 64, 102  |   |   |
| <code>\setboxmoveleft</code> .....                      | 2, 58, 60, 96   |   |   |
| <code>\setboxmoveright</code> .....                     | 2, 63, 67, 99   |   |   |
| <code>\setboxraise</code> .....                         | 65, 105   |   |   |
| <code>\setboxright</code> .....                         | 2   |   |   |
| <code>\setboxwidth</code> .....                         | 2, 54, 61, 68, 87   |   |   |
| <code>\setlength</code> 10, 11, 12, 80, 81, 82, 84, 125 |   |   |   |
| <code>\settobox@calc</code> .....                       | 109, 112, 115, 117  |   |   |
| <code>\settobox@horiz</code> .....                      | 97, 100, 111  |   |   |
| <code>\settobox@length</code> .....                     | 88, 91, 94, 108   |   |   |
| <code>\settobox@vert</code> .....                       | 103, 106, 114   |   |   |
| <code>\settoboxdepth</code> .....                       | 2, 82   |   |   |
| <code>\settoboxheight</code> .....                      | 2, 81   |   |   |
| <code>\settoboxtotalheight</code> .....                 | 2, 83   |   |   |
| <code>\settoboxwidth</code> .....                       | 2, 80   |   |   |